# How To Configure PSD Logistics SOAP Web Services

Last Updated 20/12/2022

How do I configure the SAP SOAP Web Service?

Solution

| Step	Action
1	Open a PSD Logistics Client by running PSDLogisticsClient.exe using "Run As Administrator". The default folder for this application is C:\Program Files (x86)\PSDLogistics\Client\.
2	Click the hammer icon, or select "Admin" -> "Logon As Administrator" to log in as a PSD Logistics administrator. If these options are not available, you do not have sufficient permissions to perform this operation. If this is the case, contact your PSD Logistics administrator.

| Step	Action
3	Select "Setup" -> "Web Services" -> "SOAP Web Services" then select the INPEX SAP tab sheet. INPEX URL : senderParty=&senderService=PSDLogistics_PRD&receiverParty=&receiverService=&interface=PersonReplication_Async_Out_V01&interfaceNamespace=urn:std:inpex.com.au:inpex_psd_logistics_1_0:Person INPEX User Name : PIAPPLPSD INPEX Password : Refer to Western Advance
4	 The Display Review options should only ever be turned on when testing the interfaces.

5	
	The schedule sets how frequently this web service queries for new data.
6	
	The Processing tab sets how the SAP data is imported into PSD Logistics.

| 7	
	The Timeouts tab sets various HTTP web service timeouts. Leave these options set to their default values.
8	
	The Errors tab allows administrators to be notified on any HTTP web service errors.
9	Select "Save" and "Close"

How do I configure the POUD SOAP Web Service?

Solution

| Step	Action
1	Open a PSD Logistics Client by running PSDLogisticsClient.exe using "Run As Administrator". The default folder for this application is C:\Program Files (x86)\PSDLogistics\Client\.
2	Click the hammer icon, or select "Admin" -> "Logon As Administrator" to log in as a PSD Logistics administrator. If these options are not available, you do not have sufficient permissions to perform this operation. If this is the case, contact your PSD Logistics administrator.

| Step	Action
3	Select "Setup" -> "Web Services" -> "SOAP Web Services" then select the INPEX POUD tab sheet.
	INPEX URL : http://app1pop.inpex.com.au:58800/XISOAPAdapter/MessageServlet?senderParty= &senderService=PSDLogistics_PRD&receiverParty=&receiverService=&interface=PersonReplication_Async_Out_V01&interfaceNamespace=urn:std:inpex.com.au:inpex_psd_logistics_1_0:Person INPEX User Name : PIAPPLPSD INPEX Password : Refer to Western Advance
4	
	The Display Review options should only ever be turned on when testing the interfaces.

| 5 | |
	The Schedule sets how frequently this web service queries for new data.
6	
	The Data tab outlines which data fields are sent to the POUD interface.

|	
7	**SOAP Web Services** ✕ SOAP Web Services INPEX SAP / INPEX POUD / INPEX MV Enable INPEX POUD ☑ Main / Review / Schedule / Data / Timeouts / Errors Connect Timeout [0] Seconds Send Timeout [0] Seconds ReceiveTimeout [0] Seconds [Save] [Close] [Help] The Timeouts tab sets various HTTP web service timeouts. Leave these options set to their default values.
8	**SOAP Web Services** ✕ SOAP Web Services INPEX SAP / INPEX POUD / INPEX MV Enable INPEX POUD ☑ Main / Review / Schedule / Data / Timeouts / Errors Email Group [....] ... Generate Error Files ☑ [Save] [Close] [Help] The Errors tab allows administrators to be notified on any HTTP web service errors.
9	Select "Save" and "Close"

How do I configure the MobileView SOAP Web Service?

Solution

Step	Action
1	Open a PSD Logistics Client by running PSDLogisticsClient.exe using "Run As Administrator". The default folder for this application is C:\Program Files (x86)\PSDLogistics\Client\.
2	Click the hammer icon, or select "Admin" -> "Logon As Administrator" to log in as a PSD Logistics administrator. If these options are not available, you do not have sufficient permissions to perform this operation. If this is the case, contact your PSD Logistics administrator.

| Step	Action
3	Select "Setup" -> "Web Services" -> "SOAP Web Services" then select the INPEX MV tab sheet. INPEX URL : http://10.181.37.160/asset-manager-web/services/ INPEX User Name : system INPEX Password : Refer to Western Advance
4	 The Display Review options should only ever be turned on when testing the interfaces.

| 5	
	The Schedule tab sets how frequently this web service queries for new data.
6	
	The Mappings tab sets how various MobileView data fields are mapped into PSD Logistics.

| 7 |

The Details tab sets how various PSD Logistics data fields are mapped into MobileView. |
|---|---|
| 8 |

http://10.181.37.160/asset-manager-web/pages/accessServlet?screenId=locator |

| 9	
	The Notifications tab
10	
	The Errors tab allows administrators to be notified on any HTTP web service errors.
11	Select "Save" and "Close"

How do I configure the CSS SOAP Web Service?

Solution

| Step	Action
1	Open a PSD Logistics Client by running PSDLogisticsClient.exe using "Run As Administrator". The default folder for this application is C:\Program Files (x86)\PSDLogistics\Client\.
2	Click the hammer icon, or select "Admin" -> "Logon As Administrator" to log in as a PSD Logistics administrator. If these options are not available, you do not have sufficient permissions to perform this operation. If this is the case, contact your PSD Logistics administrator.

Step	Action
3	Select "Setup" -> "Web Services" -> "SOAP Web Services" then select the CSBP CSS tab sheet. CSBP URL : http://apps-cads.csbp.com.au/Services/PSD/SwipeCardServiceHost.svc
4	 The Display Review options should only ever be turned on when testing the interfaces.

5	
	The Door Triggers page allows the card readers which are used to trigger data to be sent to the CSS web service to be configured. If new kiosks with card readers are created, the Gallagher doors need to be added to this list.
6	
	The Errors tab allows administrators to be notified on any HTTP web service errors.
9	Select "Save" and "Close"