



# How To Create A New Client In PSD Logistics

Last Updated 20/12/2022

## Quick Local Client Solution



Step	Action
1	<p>Log into MS Windows on the server hosting the PSD Logistics Server services. Run PSDLogisticsManager.exe using "Run As Administrator". The default folder for this application is C:\Program Files (x86)\PSDLogistics\Manager\.</p>  <p>The screenshot shows the PSD Logistics Manager 14.10.7 application window. The title bar reads "PSD Logistics Manager 14.10.7" and the menu bar includes "File" and "Help". The main window has four tabs: "Services", "Client", "Review", and "Test". The "Client" tab is selected, displaying a list of PSD Logistics Services. The list includes: PSD Logistics Server, PSD Logistics Cloud Server, PSD Logistics Web Server, PSD Logistics Web Services, PSD Logistics Reporting, PSD Logistics Archive Reporting, PSD Logistics Messaging, PSD Logistics Interfacing, PSD Logistics Signalling, PSD Logistics Signalling Dot Net, PSD Logistics Translating, PSD Logistics Synchronising, PSD Logistics Archiving, and PSD Logistics Monitoring. The status bar at the bottom left shows the date and time: "23/11/2022 09:56:38 AM".</p>


2 Select the Client tab sheet and click the Start button. This will create a PSD Logistics Client record for the local computer, if a client record doesn't already exist, and there is at least one spare client licence.



3 You can now run a PSD Logistics Client on this local computer and create subsequent client records in there using the following solution.

## Solution

Step	Action
1	<p>Open a PSD Logistics Client by running PSDLogisticsClient.exe using “Run As Administrator”.</p> <p>The default folder for this application is C:\Program Files (x86)\PSDLogistics\Client\.</p> 
2	<p>Click the hammer icon, or select “Admin” -&gt; “Logon As Administrator” to log in as a PSD Logistics administrator. If these options are not available, you do not have sufficient permissions to perform this operation. If this is the case, contact your PSD Logistics administrator.</p> 

Step	Action
3	<p>Select "Setup" -&gt; "Clients"</p> 
4	Click the "New" tool button then enter the hostname of the client in the editor.
5	Select "Save" and "Close".