## How To Enable The Cardholder Manager in PSD Logistics

Last Updated 20/12/2022

## Solution

This will enable PSD Logistics to add, modify and delete cardholders in the access control system.

Step	Action
1	Open a PSD Logistics Client by running PSDLogisticsClient.exe using "Run As Administrator". The default folder for this application is C:\Program Files (x86)\PSDLogistics\Client\.
	PSD Logistics Client 14.10.7 - □ × File Windows View Help      P    P      Enter your Login details. ? ×
	Login Name   Passwod   OK   Cancel   Server
	20/12/2022 07:20:50 AM Client Authenticated. Primary Server (PSD-NEILAPC4)
2	Click the hammer icon, or select "Admin" -> "Logon As Administrator" to log in as a PSD Logistics administrator. If these options are not available, you do not have sufficient permissions to perform this operation. If this is the case, contact your PSD Logistics administrator.

Step	Action
3	Select "Setup" -> "AMS Management" -> "Cardholder Management Settings".
	Cardholder Management Settings ×
	□ い □ ?
	Cardholder Management Settings
	Main Compulsory Fields Data Defaults
	Enable Cardholder Management
	Unique ID must be Unique
	Set Unique ID as PSD ID
	Unique ID Length 8 🌲
	Unique ID Prefix
	Default Photo IDs Folder
	Automatically Export Photo IDs
	Check Email Validity
	Check Mobile Validity
	Save Close Help
4	Io turn on cardholder management, tick the "Enable Cardholder Management"
	Select "Save" and "Close"

## How To Design A Cardholder Manager Layout

## Solution

This will enable you to customise the way cardholder data is entered into PSD Logistics.

Step	Action
3	Select "Setup" -> "AMS Management" -> "Cardholder Managers".
	Cardholder Manager Details X
	Cardholder Manager Details
	Name Main
	Unique ID 🗸 Title 🔽 Date Of Birth 🔽 Company 🔽 Department 🗸
	Description 🗸 Notes 🗸
	Main Operators
	Access AMT SRM Extra SAI Data VVM
	Title Access
	Access Data Fields
	Displayed Fields Available Fields
	Authorised Blank Division Site and Area Inductions
	Cards Cards Access Types
	Preview
	Save Close Help
4	Select which data fields are required, and the order that they should be displayed in
	PSD Logistics operators can be assigned different cardholder managers to limit what
	data they have access to. Select "Save" and "Close"