




How To Configure PSD Logistics To Send SMS Messages

Last Updated 20/12/2022

Solution

PSD Logistics can send SMS messages via an SMS Gateway. Your site will need access to an SMS Gateway such as telstra.tim.com.au

Step	Action
1	<p>Log into MS Windows on the server hosting the PSD Logistics Server services. Run PSDLogisticsManager.exe using "Run As Administrator". The default folder for this application is C:\Program Files (x86)\PSDLogistics\Manager\.</p> 

2	<p>Select "File" -> "Login" and log into the PSD Logistics Manager using the admin account. The default password is "admin". A number of menu items and features will be displayed.</p>  <p>The screenshot shows the PSD Logistics Manager 14.10.7 application window. The 'Services' tab is selected, displaying a list of services with 'Start' and 'Stop' buttons for each. The services listed are: PSD Logistics Server, PSD Logistics Cloud Server, PSD Logistics Web Server, PSD Logistics Web Services, PSD Logistics Reporting, PSD Logistics Archive Reporting, PSD Logistics Messaging, PSD Logistics Interfacing, PSD Logistics Signalling, PSD Logistics Signalling Dot Net, PSD Logistics Translating, PSD Logistics Synchronising, PSD Logistics Archiving, and PSD Logistics Monitoring. At the top of the services list, there are 'Start All' and 'Stop All' buttons. The status bar at the bottom shows the date and time: 23/11/2022 10:02:24 AM.</p>
3	<p>Select "Settings" -> "SMS Settings". This will display the SMS Settings window.</p>  <p>The screenshot shows the 'SMS Settings' dialog box. It contains the following fields and controls: <ul style="list-style-type: none"> SMS Provider section: <ul style="list-style-type: none"> Domain: A text input field. Prefix With Country Code: A checkbox and a text input field. Set Message Length: A checkbox and a spinner control set to 0. Set Subject to Blank: A checkbox. A 'Test' button is located to the right of the 'Set Subject to Blank' checkbox. At the bottom, there are 'Save', 'Close', and 'Help' buttons. </p>
4	<p>Enter the required account data for the SMS Gateway to enable PSD Logistics to send SMS messages.</p>
5	<p>Click "Save", then click the "Test" button to send a test email to confirm the settings are correct.</p>
6	<p>Select "Save" and "Close".</p>